

# VESSEL OWNERSHIP

## OWNERSHIP CURRENT

Provides basic information about the current vessel owners and operators.

COLUMN NAME	COMMENTS
VESSEL ID	Primary Key. Links to table LLI VESSELS
RELATIONSHIP TYPE	Ownership level coded value. Beneficial owner, Registered Owner etc. ...
COMPANY ID	Foreign Key. Unique company number
COMPANY NAME	Company name
START DATE	Date on which relationship commenced
START QUALIFIER	Qualifies <b>START DATE</b> . Exact, After / Before / About ....

## OWNERSHIP HISTORY

Contains a history of each vessel's owners and operators throughout the years.

**The historical data is more than just a list of values, the start and end dates of the period when the specified data values were in use are also provided.**

COLUMN NAME	COMMENTS
VESSEL ID	Links to table LLI VESSELS
RELATIONSHIP TYPE	Ownership level coded value. Beneficial owner, Registered Owner etc. ...
CURRENT IND	Indicates if the relationship with company is current.
COMPANY ID	Foreign Key. Unique company number
COMPANY NAME	Name of company holding relationship with vessel.
START DATE	Date on which relationship commenced
START QUALIFIER	Qualifies <b>START DATE</b> . Exact, After / Before / About ....
END DATE	Date on which relationship ended
END QUALIFIER	Qualifies <b>END DATE</b> . Exact, After / Before / About ....

## COMPANY

Holds basic details on companies. The information is stores under the unique LLI COMPANY ID's

COLUMN NAME	COMMENTS
COMPANY ID	Primary Key. Unique company identifier referenced by all child tables.
COMPANY NAME	Full company name, includes name prefix & suffix from LLI company table.
COMPANY FIRST YEAR	Year company first formed
COMPANY FIRST YEAR QUALIFIER	Date qualifier for first year. Exact, After / Before / About ....
COMPANY STATUS	Indicates the status of the company.

## COMPANY\_ADDRESS

Holds company office address and contact details.

COLUMN NAME	COMMENTS
COMPANY ID	Primary Key. Unique company identifier referenced by all child tables.
OFFICE ID	Primary Key. Unique id for office.

HEAD OFFICE IND	Y – Indicates that this record is the current head office for the company.
OFFICE STATUS	Status of the office. Null value indicates a current open office.
ADDRESS LINE 1	First line of company address.
ADDRESS LINE 2	Second line of company address.
ADDRESS LINE 3	Third line of company address.
ADDRESS LINE 4	Fourth line of company address.
TOWN/CITY	Town/City where the office is located.
COUNTY/STATE	County/State where the office is located.
POST CODE 1	Post code of the office.
POST CODE 2	Second post code of the office (required for some countries).
COUNTRY	Country where office is located – location has been decoded
TELEPHONE	Primary telephone number for the office
FAX	Primary fax number for the office
EMAIL	Primary email address for the office
WEBSITE	Primary website for the company

If you have any questions about Lloyd’s List Intelligence Made-to-measure Data, please call +44 (0) 207 017 5392 or email [info@lloydslistintelligence.com](mailto:info@lloydslistintelligence.com).